

# OneAdvisor 800 – Wireless Favorites (RA06, RA44)

## Creating Favorites

This procedure describes the process to create favorites in OneAdvisor 800 with radio analysis modules SPA06MA-O or RA44MA-O on version 4.0.2.

Favorite Creation Process:

Step	Action	Description
1	Measurement Setup: Note: Measurement setups are specific to radio analysis platforms SPA06MA-O or RA44MA-O.	Create a measurement setup or load an existing measurement setup.
2	Select the following: <ul style="list-style-type: none"> <li>- {Save}</li> <li>- {Create Favorites}</li> <li>- {Favorites Title}</li> <li>- Enter the file name</li> <li>- {Enter}</li> <li>- {Create}</li> </ul>	<p style="text-align: center;">Create Favorites</p>
3	Favorites Page, select: <ul style="list-style-type: none"> <li>- {Home}</li> <li>- {Favorites}</li> </ul>	<p style="text-align: center;">Display Favorites</p>