

QUICK CARD

Updating Software via USB

This quick card outlines how to upgrade the OneAdvisor 800 to the latest software revision using a USB Flash Drive. Note: the software must be downloaded to a PC and **extracted** to a formatted 4GB to 16GB USB flash drive. If the downloaded file is copied directly to the USB flash drive, the upgrade will fail.

EQUIPMENT REQUIREMENTS








Equipment Requirements:

- Laptop or Personal Computer with Internet Access
- 4GB to 16GB USB Flash Drive



Figure 1: Equipment Requirements

FORMAT USB FLASH DRIVE

1. Press the Power button  on the top panel to turn on the OneAdvisor.
2. Insert the USB Flash Drive into a USB port under the flap on the top panel of the OneAdvisor 800 
3. Tap  Home to display the Home Screen.
4. Tap  System to display the **System menu**.
5. Tap the **Removable Storage** Icon  to show the Removable Storage menu.
6. Tap  Format to format the USB Flash Drive.
7. Tap  Eject and remove the USB Flash Drive from the USB port of the test set.
8. Insert the formatted USB flash drive into your Laptop or Personal Computer.




Figure 2: System Menu




Figure 3: Removable Storage Menu




QUICK CARD

DOWNLOAD ARCHIVE AND EXTRACT TO USB FLASH DRIVE

1. On Laptop or Personal Computer, open an Internet browser and navigate to the software update portal for the OneAdvisor 800:

▶ <http://ONA-800.updatemyunit.net/>

2. Click a Flag icon to download software from the nearest server:

- ▶  Europe Server
- ▶  North America Server
- ▶  Singapore Server

3. Select “[Run](#)” or “[Open file](#)” to extract the upgrade files from your Downloads directory to a USB drive. If you save the .exe file directly to the USB flash drive, the update will fail.




Figure 4: updatemyunit.net

4. If your browser displays a warning that the update is an unrecognized or uncommon app, click “...”, “Keep”, “See more”, “More info”, “Keep anyway” and/or “Run anyway” to continue.

5. Enter or browse to the path of the USB Stick and press the **OK** button to extract update files to the USB Flash Drive.









Figure 5: Enter or Browse to the path of the USB Flash Drive

QUICK CARD

UPGRADE TEST SET

1. Eject and remove the USB Flash Drive from the Laptop or Personal Computer.
2. Insert the USB Flash Drive into a USB port on the top of the OneAdvisor.
3. Plug the OneAdvisor test set into AC power. You cannot update the software while running on battery.
4. Tap  to display the Home Screen.
5. Tap  to display the **System menu**.
6. Tap the **Upgrade** Icon  to show the Upgrade menu.
7. Select USB for the upgrade method.

8. Tap  and follow screen prompts to complete the software upgrade.




Figure 6: System Menu




Figure 7: Upgrade Menu